



# Floppy Knit Hat

WR1792



Designed by Edie Eckman

Directions are for Small; changes for Medium are in parentheses.

RED HEART® “Eco-Ways™”: 2 balls 1821 Blue Cloud.

Knitting Needles: 4.5mm [US 7] and 5mm [US 8].  
Yarn needle.

**GAUGE:** 24 sc = 4”; 20 rows = 4” in Twisted Rib using larger needles. **CHECK YOUR GAUGE. Use any size needles to obtain the gauge.**

**Head Circumference: 17 (18)”**

**Twisted Rib** (multiple of 4 sts + 2)

**Row 1 (RS):** P2, \*RT, p2; repeat from \* across.

**Row 2:** K2, \*p2, k2; repeat from \* across.

Repeat Rows 1 and 2 for Twisted Rib Pattern.

### HAT

With smaller needles, cast on 106 (112) sts.

**Row 1 (WS):** K2,\* p2, k2; repeat from \* across.

**Row 2:** P2, \*k2, p2; repeat from \* across.

Repeat Rows 1 and 2 until piece measures 4 1/2” from beginning, end with a wrong side row.

Change to larger needles and work in Twisted Rib until piece measures 12 (12 1/2)” from beginning.  
Bind off in pattern.

### FINISHING

Fold in half crosswise and sew sts of last row together for top of Hat. Sew side seam. Weave in ends.



RED HEART® “Eco-Ways™”, Art.E750  
(4 ounce/186yard ball).

**ABBREVIATIONS:** K = knit; mm = millimeters; P = purl; st(s) = stitch (es); \* = repeat whatever follows the \* as indicated.

### Special Abbreviation:

**RT:** (Right Twist) Knit next 2 sts tog, leaving sts on needle, knit first st once more, drop both sts from needle.

